



Windows Server 2008 R2



Essentials

Windows Server 2008 R2 Essentials

Installation, Deployment and Management



Windows Server 2008 R2 Essentials – First Edition

© 2010 Payload Media. This eBook is provided for personal use only. Unauthorized use, reproduction and/or distribution strictly prohibited. All rights reserved.

The content of this book is provided for informational purposes only. Neither the publisher nor the author offers any warranties or representation, express or implied, with regard to the accuracy of information contained in this book, nor do they accept any liability for any loss or damage arising from any errors or omissions.

Find more technology eBooks at <http://www.eBookFrenzy.com>.

Table of Contents

Chapter 1.	About Windows Server 2008 R2 Essentials	12
Chapter 2.	Windows Server 2008 R2 Editions and System Requirements.....	13
2.1	CPU Requirements	13
2.2	Windows Server 2008 R2 Foundation Edition	13
2.3	Windows Server 2008 R2 Standard Edition	13
2.4	Windows Server 2008 R2 Enterprise Edition	14
2.5	Windows Server 2008 R2 Datacenter Edition.....	14
2.6	Windows Web Server 2008 R2.....	14
2.7	Windows Server 2008 R2 Features Matrix.....	14
2.8	Windows Server 2008 Hardware Requirements.....	16
Chapter 3.	Performing a Clean Windows Server 2008 R2 Installation.....	17
3.1	Obtaining Windows Server 2008 R2	17
3.2	Starting the Installation Process	17
3.3	Disk and Partition Management	19
3.4	Accessing the Command Prompt during Installation.....	20
Chapter 4.	Performing a Windows Server 2008 R2 Upgrade.....	21
4.1	Windows Server 2008 R2 Upgrade Paths	21
4.2	How an Upgrade to Windows Server 2008 R2 Works	22
4.3	Performing the Upgrade	22
4.4	Windows Server 2008 R2 Compatibility Report.....	24
4.5	Accessing the Command Prompt during Installation.....	24
Chapter 5.	Windows Server 2008 R2 Command-line Tools.....	26
5.1	Accessing the Command Window.....	26
5.2	Windows Server 2008 R2 Command-line Tool Summary	26
5.3	Displaying a List of Commands.....	33
5.4	Obtaining Help Information about Command-line Tools	33
Chapter 6.	Configuring BitLocker Drive Encryption on Windows Server 2008 R2	34

6.1	BitLocker Prerequisites	34
6.2	Enabling BitLocker Drive Encryption	35
6.3	Creating Partitions for BitLocker Drive Encryption	37
6.4	Enabling BitLocker Drive Encryption	39
6.5	Changing Group Policy for BitLocker.....	40
6.6	Performing the Encryption and Generating Keys	41
6.7	Regenerating BitLocker Startup Keys and Recovery Passwords	43
6.8	Disabling BitLocker Drive Encryption	44
Chapter 7.	Configuring Windows Server 2008 R2 Remote Administration	45
7.1	Remote Administration Using Server Manager	45
7.2	What is Remote Desktop?.....	47
7.3	Enabling Remote Desktop Administration on the Remote Server	47
7.4	Controlling Remote Desktop Access	49
7.5	Starting the Remote Desktop Client	50
7.6	Remote Desktop Client Configuration Options.....	51
7.7	Remote Session Tracking	52
7.8	Logging out from a Remote Desktop Session	53
7.9	Running Multiple Remote Desktops	53
Chapter 8.	Adding New GPT and MBR Disks to Windows Server 2008 R2 Systems	56
8.1	An Overview of MBR and GPT Partitions Styles.....	56
8.2	Understanding MBR Disks.....	56
8.3	Understanding GPT Disks	57
8.4	Initializing a New Disk	57
8.5	Converting Disks between MBR and GPT Partition Styles	59
Chapter 9.	Creating and Managing MBR Disk Partitions on Windows Server 2008 R2 Basic Disks	61
9.1	Creating Partitions on an MBR Basic Disk	61
9.2	Formatting a Volume using Disk Management.....	65

9.3	Formatting a Volume from the Command Line	65
9.4	Assigning and Changing Drive Letters and Mount Points	67
9.5	Assigning and Changing Drive Letters and Mount Points from the Command Line.....	67
Chapter 10. Creating and Managing GPT Disk Partitions on Windows Server 2008 R2 Basic Disks		70
10.1	An Overview of GPT Partition Types	70
10.2	Creating Primary Partitions on a GPT Basic Disk.....	71
10.3	Formatting a Volume using Disk Management.....	74
10.4	Formatting a Volume from the Command Line	74
10.5	Assigning and Changing Drive Letters and Mount Points	75
10.6	Assigning and Changing Drive Letters and Mount Points from the Command Line.....	76
Chapter 11. Extending and Shrinking Windows Server 2008 R2 Partitions and Volumes		78
11.1	Shrinking a Windows Server 2008 R2 Partition Using Disk Management	78
11.2	Shrinking a Partition from the Command Line.....	79
11.3	Extending a Partition Using Disk Management.....	80
11.4	Extending a Partition from the Command Line	81
Chapter 12. Creating and Managing Simple and Spanned Volumes on Windows Server 2008 R2		84
12.1	An Overview of Dynamic Disks.....	84
12.2	Converting Basic Disks to Dynamic Disks with Disk Management	85
12.3	Converting Basic Disks to Dynamic Disks from the Command Line.....	86
12.4	Creating a New Spanned Volume using Disk Management.....	87
12.5	Creating a New Spanned Volume from the Command Prompt.....	89
Chapter 13. Creating and Managing Windows Server 2008 R2 Striped (RAID 0) Volumes		93
13.1	An Overview of Striped (RAID 0) Volumes	93
13.2	Creating a Striped (RAID 0) Volume using Disk Management	93
13.3	Creating a Striped (RAID 0) Volume from the Command Prompt	94
13.4	Recovering a Striped Volume.....	96

Chapter 14. Configuring Disk Mirroring (RAID 1) on Windows Server 2008 R2.....	97
14.1 An Overview of Disk Mirroring (RAID 1).....	97
14.2 Creating a Mirrored (RAID 1) Set using Disk Management.....	97
14.3 Creating a Mirrored (RAID 1) Volume from the Command Prompt	98
14.4 Adding a Mirror to an Existing Volume	100
14.5 Breaking and Removing Mirrored Sets	103
14.6 Recovering a Mirrored Set	103
Chapter 15. Mirroring Windows Server 2008 R2 GBT and MBR Boot and System Disks.....	104
15.1 An Overview of GPT and MBR Partition Styles	104
15.2 Mirroring Boot and System Volumes on an MBR Disk using Disk Management.....	104
15.3 Mirroring Boot and System Volumes on an MBR Disk from the Command Prompt...	106
15.4 Mirroring Boot and System Volumes on a GPT Disk	108
Chapter 16. Configuring and Managing RAID 5 on Windows Server 2008 R2	113
16.1 An Overview of RAID 5	113
16.2 Configuring RAID 5 Using Windows Server 2008 Disk Management	113
16.3 Configuring RAID 5 from the Command Prompt using DiskPart.....	115
16.4 Fixing RAID 5 Problems	117
Chapter 17. Windows Server 2008 R2 Remote Desktop (RD) Services.....	118
17.1 Installing Remote Desktop Services	118
17.2 Adding Users to the Remote Desktop Users Group.....	122
17.3 Accessing Remote Desktop Services from the Client.....	124
17.4 Remote Desktop Client Configuration Options.....	125
17.5 Logging out from a Remote Desktop Session	126
17.6 Running Multiple Remote Desktops	126
Chapter 18. Installing Applications for Windows Server 2008 R2 Remote Desktop Services..	129
18.1 Understanding Remote Desktop Services Operating Modes	129
18.2 Installing Remote Desktop Applications using the Control Panel.....	130
18.3 Remote Desktop Services Application Compatibility Scripts.....	132

18.4	Summary	133
Chapter 19.	Configuring RemoteApps on Windows Server 2008 R2	134
19.1	Preparing the RD Session Host for RemoteApps	134
19.2	What are RemoteApps?	134
19.3	Configuring a Application as a RemoteApp	135
19.4	Making RemoteApps Available to Users via RD Web Access.....	138
19.5	Making RemoteApps Available to Users via Windows Installer Packages	140
19.6	Making RemoteApps Available to Users via .RDP Files.....	141
Chapter 20.	Configuring Windows Server 2008 R2 RD Web Access	143
20.1	Installing RD Web Access Role Service.....	143
20.2	Accessing the RD Web Access Page	145
20.3	Configuring RemoteApps for RD Web Access.....	147
Chapter 21.	Deploying a Windows Server 2008 R2 Remote Desktop Server Farm using RD Connection Broker	152
21.1	An Overview of the Remote Desktop Connection Broker	152
21.2	Prerequisites for Implementing RD Connection Broker	153
21.3	Installing the Remote Desktop Session Broker	153
21.4	Adding RD Sessions Hosts to the RD Connection Broker.....	153
21.5	Joining RD Session Hosts to an RD Connection Broker	156
21.6	Configuring the RD Session Broker	159
Chapter 22.	Configuring a Windows Server 2008 R2 Remote Desktop Services License Server	163
22.1	Installing the Remote Desktop Services License Server.....	163
22.2	Activating the RD License Server.....	165
22.3	Installing Client Access Licenses (CAL)	167
22.4	Configuring Licensing Settings on RD Session Hosts.....	168
Chapter 23.	Managing Windows Server 2008 R2 Disk Quotas.....	170
23.1	An Overview of Disk Quotas.....	170

23.2	Configuring Disk Quotas.....	170
23.3	Configuring Disk Quotas for Individual Users	172
23.4	Querying Quotas from the Command Prompt	174
Chapter 24.	Repairing and Defragmenting Windows Server 2008 R2 Disks	177
24.1	Using Check Disk to Scan For and Fix File System Errors	177
24.2	Running Check Disk from the Command-prompt.....	178
24.3	Defragmenting Disks with Disk Defragmenter.....	180
24.4	Automated Disk Defragmentation	181
24.5	Defragmenting Disks from the Command-line	182
Chapter 25.	Configuring Windows Server 2008 R2 File Sharing.....	186
25.1	Standard and Public File Sharing.....	186
25.2	Enabling Windows Server 2008 R2 File Sharing.....	186
25.3	Creating Shared Folders with Windows Explorer	189
25.4	Creating Shared Folders on Remote Servers with Computer Management	194
25.5	Creating Hidden Shares.....	196
25.6	Understanding and Configuring Share Permissions.....	196
Chapter 26.	Using NET SHARE to Configure Windows Server 2008 R2 File Sharing	199
26.1	Net Share Command-line Syntax	199
26.2	Getting Share Information using Net Share	199
26.3	Creating a Share using Net Share.....	200
26.4	Using Net Share to Delete a Share from a Local Server.....	201
26.5	Using Net Share to Delete a Share from a Remote Server	201
Chapter 27.	Understanding Windows Server 2008 R2 File and Folder Ownership and Permissions	202
27.1	Ownership of Files and Folders	202
27.2	Taking and Transferring Windows Server 2008R2 File and Folder Ownership.....	202
27.3	File and Folder Permission Inheritance.....	204
27.4	Basic File and Folder Permissions	205

27.5	Special File and Folder Permissions	207
27.6	Effective File and Folder Permissions.....	209
Chapter 28.	Auditing Windows Server 2008 R2 File and Folder Access.....	211
28.1	Enabling File and Folder Auditing.....	211
28.2	Configuring which Files and Folders are to be Audited	212
Chapter 29.	Configuring Volume Shadow Copy on Windows Server 2008 R2.....	215
29.1	Shadow Copy Considerations.....	215
29.2	Using Computer Management to Enable and Configure Volume Shadow Copies.....	215
29.3	Restoring an Entire Volume	219
29.4	Configuring and Enabling Shadow Copy from the Command Line	220
29.5	Restoring Shadow Copy Snapshots from Clients	224
Chapter 30.	Building a Windows Server 2008 R2 Network Load Balancing Cluster	226
30.1	An Overview of Network Load Balancing Clusters.....	226
30.2	Network Load Balancing Models	227
30.3	Configuring Port and Client Affinity	227
30.4	Installing the Network Load Balancing Feature	228
30.5	Building a Windows Server 2008 R2 Network Load Balanced Cluster.....	228
30.6	Adding and Removing Network Load Balanced Cluster Nodes	234
Chapter 31.	Configuring Windows Server 2008 R2 DHCP Servers	236
31.1	Installing the DHCP Server Role	236
31.2	Authorizing DHCP Servers in Active Directory	238
31.3	Understanding DHCP Scope Types.....	239
31.4	Configuring IPv4 Scopes Using the DHCP Console.....	239
31.5	Configuring DHCP Reservations	243
Chapter 32.	Managing a Windows Server 2008 R2 DHCP Server from the Command Line	247
32.1	Installing the DHCP Feature from the Command Line.....	247
32.2	Authorizing DHCP Servers in Active Directory	247
32.3	Configuring Scopes at the Command Prompt.....	247

32.4	Activating and Deactivating DHCP Scopes using Netsh	250
32.5	Terminating a DHCP Lease using Netsh	251
32.6	Configuring DHCP Reservations using Netsh	251
32.7	Configuring DHCP Conflict Detection	252
32.8	Backing Up and Restoring DHCP Configuration Information	253
Chapter 33.	Setting Up a Windows Server 2008 R2 Print Server	254
33.1	Installing the Print Server	254
33.2	Print Services Management Tools	255
33.3	Adding Network Printers to the Print Server using Auto-detect	256
33.4	Manually Adding Network Printers to a Print Server	260
33.5	Adding a Locally Connected Printer	261
Chapter 34.	Managing Windows Server 2008 R2 Print Services	265
34.1	Managing Remote Print Servers	265
34.2	Migrating Printers and Queues between Servers	267
34.3	Configuring Printer Permissions	270
34.4	Changing Printer Ownership	273
34.5	Printer Pooling Configuration	274
34.6	Configuring Printer Availability and Priority	275
Chapter 35.	Related eBook Publications	277

Chapter 1. About Windows Server 2008 R2 Essentials

This is the second edition of Windows Server 2008 Essentials and has been updated to reflect the new features and functionality introduced by the second release of Microsoft's highly regarded server operating system, known as Windows Server 2008 R2.

Consisting of 35 chapters of detailed, in depth and practical information, Windows Server 2008 R2 Essentials is intended to cover all aspects of installing, configuring and administering Windows Server 2008 R2 systems. Whether new to Microsoft's Windows Server operating systems, or upgrading from Windows Server 2003, this eBook is designed to help the reader traverse the learning curve as rapidly as possible.

Topics covered in this publication include installation and upgrades, networking configuration, terminal services, disk and partition management, RAID configuration, security, BitLocker encryption, remote desktop access, print services, resource sharing, clustering, load balancing and user permission management.

In addition to providing a detailed overview of the features and functions of Windows Server 2008 R2, this on-line book also provides practical, step by step examples intended to bridge the gap between text book theory and real world practice.

Chapter 2. Windows Server 2008 R2 Editions and System Requirements

Before embarking on the installation of Windows Server 2008 R2, it is important to first gain an understanding of the different editions available and the corresponding hardware requirements. It is also important to be aware of the upgrade options available with each edition. With this objective in mind, this chapter will focus on providing an overview of both the different Windows Server 2008 R2 editions and the recommended hardware requirements.

2.1 CPU Requirements

The first of note for user familiar with the first version of Windows Server 2008 is that the R2 edition is only available for 64-bit systems. Whilst some editions of the original Windows Server 2008 operating system were available in 32-bit versions, this is now longer the case for the R2 version.

2.2 Windows Server 2008 R2 Foundation Edition

The Foundation edition of Windows Server 2008 is the new entry level edition of Windows Server 2008 and is designed specifically with the small business in mind. It is the least expensive of the various editions and lacks some of the more advanced functionality typically found in the higher end editions such as full Active Directory support and Hyper-V virtualization capabilities. In addition, the Foundation edition limits some of the included features, such as restricting the number of concurrent remote desktop services connections to 50 and is able to access a maximum of 1 processor and 8GB of RAM.

2.3 Windows Server 2008 R2 Standard Edition

Windows Server 2008 R2 Standard is another one of Microsoft's entry level server offerings (alongside Windows Web Server R2 2008 and Windows Server R2 2008 Foundation). As previously stated, whilst the original version of Windows Server 2008 supported both 32-bit and 64-bit versions, the R2 version supports only 64-bit processors. In terms of hardware Standard Edition supports up to 4GB of RAM and 4 processors.

Windows Server 2008 is primarily targeted and small and mid-sized businesses (SMBs) and is ideal for providing domain, web, DNS, remote access, print, file and application services. Support for clustering, however, is notably absent from this edition.

An upgrade path to Windows Server 2008 R2 Standard is available from Windows Server 2008, Windows 2000 Server and Windows Server 2003 Standard Edition.

2.4 Windows Server 2008 R2 Enterprise Edition

Windows Server 2008 R2 Enterprise Edition provides greater functionality and scalability than the Standard Edition. As with Standard Edition both 32-bit and 64-bit versions are available. Enhancements include support for as many as 8 processors and up to 2TB of RAM.

Additional features of the Enterprise edition include support for clusters of up to 16 nodes and Active Directory Federated Services (AD FS).

Windows Server 2000, Windows 2000 Advanced Server, Windows Server 2003 Standard Edition and Windows Server 2003 Enterprise Edition may all be upgraded to Windows Server 2008 R2 Enterprise Edition.

2.5 Windows Server 2008 R2 Datacenter Edition

The Datacenter edition represents the top end of the Windows Server 2008 R2 product range and is targeted at mission critical enterprises requiring stability and high uptime levels.

Windows Server 2008 R2 Datacenter edition supports up to 2TB of RAM and a minimum of 8 processors up to a maximum of 64.

Upgrade paths to Windows Server 2008 R2 Datacenter Edition are available from the Datacenter editions of Windows Server 2008, Windows 2000 and 2003.

2.6 Windows Web Server 2008 R2

Windows Web Server R2 2008 is essentially a version of Windows Server 2008 R2 designed primarily for the purpose of providing web services. It includes Internet Information Services (IIS) 7.0 along with associated services such as Simple Mail Transfer Protocol (SMTP) and Telnet. It supports up to 4 processors but RAM is limited to 32GB.

As with other entry level editions, Windows Web Server 2008 R2 lacks many of the features present in other editions such as clustering, BitLocker drive encryption, multipath I/O, Windows Internet Naming Service (WINS), Removable Storage Management and SAN Management.

2.7 Windows Server 2008 R2 Features Matrix

Now that we have covered in general terms the various different editions of Windows Server 2008 R2 we can now look in a little more detail at a feature by feature comparison of the four different editions. This is outlined in the following feature matrix:

Feature	Enterprise	Datacenter	Standard	Itanium	Web	Foundation
Active Directory Certificate	Yes	Yes	Limited	No	No	Limited

Services						
Active Directory Domain Services	Yes	Yes	Yes	No	No	Yes
Active Directory Federation Services	Yes	Yes	No	No	No	No
Active Directory Lightweight Directory Services	Yes	Yes	Yes	No	No	Yes
Active Directory Rights Management Services	Yes	Yes	Yes	No	No	Yes
Application Server	Yes	Yes	Yes	Yes	No	Yes
DHCP Server	Yes	Yes	Yes	No	No	Yes
DNS Server	Yes	Yes	Yes	No	Yes	Yes
Fax Server	Yes	Yes	Yes	No	No	Yes
File Services	Yes	Yes	Limited	No	No	Limited
Hyper-V	Yes	Yes	Yes	No	No	No
Network Policy and Access Services	Yes	Yes	Limited	No	No	Limited
Print and Document Services	Yes	Yes	Yes	No	No	Yes
Remote Desktop Services	Yes	Yes	Limited	No	No	Limited
Web Services (IIS)	Yes	Yes	Yes	Yes	Yes	Yes
Windows Deployment Services	Yes	Yes	Yes	No	No	Yes
Windows Server Update Services (WSUS)	Yes	Yes	Yes	No	No	Yes

2.8 Windows Server 2008 Hardware Requirements

Before investing time and resources into downloading and installing Windows Server 2008, the first step is to gain an appreciation of the hardware requirements necessary to effectively run the operating system. The following table provides an overview of Microsoft's recommended minimum hardware:

Category	Minimum / Recommended Requirements
Processor	<ul style="list-style-type: none"> • Minimum: 1.4GHz (x64 processor) • Recommended: 2GHz or faster <p>Note: For Itanium based systems an Intel Itanium 2 processor is required.</p>
Memory	<ul style="list-style-type: none"> • Minimum: 512MB RAM • Recommended: 2GB RAM or greater • Maximum: 8GB (Foundation) 32GB (Standard) or 2TB (Enterprise, Datacenter and Itanium-Based Systems)
Available Disk Space	<ul style="list-style-type: none"> • Minimum: 10GB • Recommended: 40GB or greater <p>Note: Systems with RAM in excess of 16GB will require greater amounts of disk space to accommodate paging, hibernation, and dump files</p>
Drive	DVD-ROM drive
Display and Peripherals	<ul style="list-style-type: none"> • Super VGA or greater-resolution monitor (800x600) • Keyboard • Microsoft Mouse or compatible pointing device

As with the specified system requirements for all Windows systems it is best to aim for the *Recommended* values rather than the *Minimum* values to ensure acceptable levels of performance. For example, whilst it is possible to run Windows Server 2008 in 512MB of RAM it is unlikely that performance levels will be optimal with such a configuration.

Chapter 3. Performing a Clean Windows Server 2008 R2 Installation

Windows Server 2008 R2 may be installed using a number of different approaches. One such approach involves installing an entirely new instance of the operating system on a disk or partition such that any previous operating system installation and associated data are destroyed. Another option is to perform an upgrade of an existing Windows installation such that user data, settings and applications are retained. In addition, the installation may be performed interactively where the user is required to respond to prompts during the installation, or unattended where pre-configured responses are supplied by an *answer* file.

The topic of this chapter is the clean, interactive installation of Windows Server 2008 R2. The subject of upgrades is covered in *Chapter 4 - Performing a Windows Server 2008 R2 Upgrade*.

3.1 Obtaining Windows Server 2008 R2

If you do not already have access to the Windows Server 2008 R2 installation media this can be downloaded from the Microsoft web site. Downloads are available for the Foundation, Standard, Enterprise, Datacenter and Web editions of the operating system. For detailed information on the features provided with each edition refer to *Chapter 2 - Windows Server 2008 R2 Editions and System Requirements*.

All downloadable editions can be run either without a key (i.e. in evaluation mode) or with a key (if a license has already been purchased). The evaluation period lasts for 180 days.


The Windows Server 2008 R2 download is provided in the form of an ISO image which may be burned to a DVD and subsequently be used to perform the installation.

3.2 Starting the Installation Process

Windows Server 2008 R2 may be installed either by booting from the installation DVD or by logging into the previously installed operating system as an administrator and launching the *Setup* tool on the DVD (typically this will auto-run when the DVD is inserted into the drive). The following figure shows the initial installation screen:



Select the appropriate language preferences and click *Next* to proceed with the installation process. On the subsequent screen the installation may be started by clicking on the *Install now* button. Alternatively, the *What To Know Before Installing Windows Server 2008* link will provide information on system requirements and advice about issues such as application and driver compatibility. Clicking on *Install now* proceeds to the *Operating System Selection* screen shown in the following figure:




Having selected the edition of Windows Server 2008 R2 that you wish to install, click *Next* to proceed to license terms screen. Read and agree (assuming you do agree) to the license terms and proceed to the next screen where the options to upgrade or perform a custom installation are provided. If the installer was invoked by booting from the DVD, or the host operating system is not suitable for upgrade, only the custom installation option will work at this point. Select this option to proceed.

3.3 Disk and Partition Management

The next screen provides an interface for selecting and configuring disks and partitions for the installation. Initially, this screen displays a list of physical disk drives available on the system together with any pre-existing partitions on those disks.

Clicking on the *Drive options (advanced)* option displays a number of options including the deletion, creation and formatting of partitions on the listed disk drives. In addition, the *Load*

driver option allows any driver necessary to access a disk drive to be loaded into to system so that the device may be used as an installation destination. For the purposes of this installation, the entire disk drive will be used as the installation target. The following figure shows a single, unpartitioned disk drive with the *Drive options* displayed:



Click *Next* to begin the installation process. A new screen will appear listing the progress of the installation and highlighting the fact that the system will reboot a number of times during the installation.

3.4 Accessing the Command Prompt during Installation

At any point during the setup process (except when the installation is actually being performed) *Shift+F10* may be pressed to gain access to the command-prompt. From within this command prompt window most of the standard Windows Server 2008 R2 command-line tools are available allowing tasks to be performed that might otherwise not be possible from within the setup interface. A full list of available commands and respective descriptions can be found in *Chapter 5 - Windows Server 2008 R2 Command-line Tools*.